

General

1. Prepare your data
 - a. Either, a folder contains only files of one channel, or
 - b. In each folder we have the structure channel1/, channel2/... containing the corresponding data.
2. Open convertVideos.py (e.g. with spyder)
3. Adjust parameters (see below) and run the file.
4. Type convertVideos() into shell / console in order to start the process.

Variables and Parameters

We make an example:

- Zoo: **FancyZoo**
- Species: **Wildebeest**
- [videonumber **1** (only if the folder contains only the files of one channel)]
- Path to the .asf files: **Server/Wildebeest/FancyZoo/Box_1/, ..., Server/Wildebeest/FancyZoo/Box_3/** (3 channels)
- Recording per night: 17:00 to 06:59:59 and per day 07:00 to 16:59:59
- Resulting video files (output): **YYYY-MM-DD_Wildebeest_FancyZoo_1.avi, ..., YYYY-MM-DD_Wildebeest_FancyZoo_3.avi**

| Parameter | Type | Explanation | Example |
|----------------------|--------|--|--|
| PATH_TO_VID | String | <ul style="list-style-type: none"> Path to the videofiles created by lupus (one folder, one channel) or various subfolders each containing the files of one channel. | PATH_TO_VID = ,Server/Wildebeest/FancyZoo/ |
| CONVERT_WHOLE_FOLDER | Bool | <ul style="list-style-type: none"> True: Multiple subfolders (for each channel one) exist. False: Path directly to the .asf files. Beware: The subfolders need to be named ,Box_i' for any integer i. | CONVERT_WHOLE_FOLDER = True |
| ALREADY_SORTED | Bool | <ul style="list-style-type: none"> True: the video files per night were already moved to a subfolder (not standard). False: all .asf files per channel are contained in one folder without subfolders, the script creates different files per night and per day automatically. | ALREADY_SORTED = False |
| ANIMAL_NAME | String | <ul style="list-style-type: none"> Species | ANIMAL_NAME = ,Wildebeest' |
| VIDEO_NUMBER | String | <ul style="list-style-type: none"> Videonumber, as a string! Only used if CONVERT_WHOLE_FOLDER = False | VIDEO_NUMBER = ,1' |
| ZOO_NAME | String | <ul style="list-style-type: none"> Name of Zoo, may not contain special characters beside -. | ZOO_NAME = ,FancyZoo' |

| | | | |
|------------------|--------|---|-------------------------|
| ORIGINAL_RES | Bool | <ul style="list-style-type: none"> • True: original resolution of .asf files is kept. • False: rescaling to a width of MAXIMAL_WIDTH. | ORIGINAL_RES = False |
| MAXIMAL_WIDTH | Int | <ul style="list-style-type: none"> • Upscaling is not possible, only downscaling! | MAXIMAL_WIDTH = 1280 |
| ORIGINAL_FPS | Bool | <ul style="list-style-type: none"> • True: Keeps the fps of the .asf files. • False: Output has OUTPUT_FPS many frames per second. | ORIGINAL_FPS = False |
| OUTPUT_FPS | Int | <ul style="list-style-type: none"> • How many fps should the output video have? Needs to be smaller or equal to the original fps of the .asf files and a divisor. | OUTPUT_FPS = 1 |
| NIGHT_TIME_BEGIN | String | <ul style="list-style-type: none"> • Time to which a night recording starts, will be used to detect the time in LUPUS structure, e.g.: • HVCR_ch3_main_20181128170000_20181128180000.asf | NIGHT_TIME_BEGIN = ,17' |
| DAY_TIME_BEGIN | String | <ul style="list-style-type: none"> • Time to which a day recording starts, will be used to detect the time in LUPUS structure, e.g.: • HVCR_ch3_main_20181128070000_20181128080000.asf • If no day recordings are conducted, this can be set to the empty string "". | DAY_TIME_BEGIN = ,07' |
| | | Testing variables | |
| KI_EXPORT | Bool | <ul style="list-style-type: none"> • True: Additionally, a grayscale variant is created. | KI_EXPORT = False |
| TEST_PROC | Bool | <ul style="list-style-type: none"> • True: If set to true, only the first 10 seconds of each videofile (.asf) will be used, this allows to test the program / structure in short time. | TEST_PROC = False |

Requirements

Python

- Python >= 3.5
- numpy, opencv

Structure

- .asf-files as given through some variants of LUPUS or Technaxx:
 - PREFIX_CHANNEL_FILLWORD_YYYYMMDDHHMMSS_YYYYMMDDHHMMSS.asf
 - E.g.: HVCR_ch3_main_20181128100636_20181128110001
 - E.g.: LUPUS_ch3_main_20181128100636_20181128110001